# Dell License Manager Version 1.1

**Release Notes** 



### **Release Notes**

### License Manager

Dell License Manager is a one-to-many license deployment and reporting tool for integrated Dell Remote Access Controller (iDRAC) and Dell chassis management controller (CMC) licenses. Dell License Manager can also inventory licensable systems to report the licensing status and currently enabled management controller feature level. Use Dell iDRAC licenses to enable server management capabilities such as the virtual media and remote console support currently available in the Enterprise iDRAC feature set. Use Dell CMC licenses to enable chassis management capabilities such as console integration, remote access, mutli-chassis management, server cloning, and so on. To use the license manager, inventory licensable servers and deploy licenses obtained from the online licensing portal (http://www.dell.com/support/retail/lkm).

#### Version 1.1

Release Date: February 2014 Previous Version 1.0.1

## **Importance**

OPTIONAL: Dell recommends the customer review specifics about the update to determine if it applies to your system. The update contains changes that impact only certain configurations, or provides new features that may/may not apply to your environment.

### What's New

- Support for CMC licenses on Dell PowerEdge VRTX and Dell PowerEdge FX and FX2 enclosures.
- Support for Dell PowerEdge FC420, FC620, and FM120x4 sleds.
- Support for removing a license from a system.
- New grouping for Modular Systems in the Systems view.

## **Installation Prerequisites**

Microsoft .NET Framework 4.5

http://www.microsoft.com/en-us/download/details.aspx?id=30653

#### Windows Remote Management (WinRM) 2.0 or later

Part of Windows Management Framework Core package <a href="http://support.microsoft.com/kb/968930">http://support.microsoft.com/kb/968930</a>

This functionality is included in Microsoft Windows 7 and Windows Server 2008 R2.

The WinRM prerequisites are also available through Microsoft Windows Update.

## **Hardware And Software Requirements**

#### **Disk Space**

200 MB (minimum)

#### Memory (RAM)

2 GB (minimum)

#### Network

100 Mbps

#### **Screen Resolution**

1024 x 768

1600 x 1200 for German users

#### **Operating System**

Microsoft Windows 7 Windows Server 2008 R2 Windows Server 2008 (SP2 or later) Windows Server 2012

Windows Server 2012 R2

Both 64-bit and 32-bit versions are supported.

## Installation

To install Dell License Manager, download and run the installer. For more information on installing Dell License Manager, see the *Dell License Manager User Guide* at **dell.com/OpenManageManuals**.

## Uninstallation

Dell License Manger can be uninstalled from the Windows Control Panel, Programs and Features option.

## **Global Support**

For technical support, see www.dell.com/support.

Copyright © 2014 Dell Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. Dell<sup>TM</sup> and the Dell logo are trademarks of Dell Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.